

How To Find The MAC Address For Your Device

Access to the school Wi-Fi will be granted once your device MAC Address is received.

iPad

- Tap on **Settings**
- Tap on **General**
- Navigate to and tap on **About**
- Scroll down to **Wi-Fi Address**
- The characters next to Wi-Fi Address make up your MAC Address.

Nook

- Press the **Home** button
- On the Home menu, tap **Settings**
- Find the entry for MAC Address

Nook Color

- Tap the **Nav Arrow** at the bottom of the screen to display the **Quick Nav Bar**
- Tap **Settings**
- Tap **Device Info**
- Tap **About Your NOOK**
- Find the entry for MAC Address

Kindle / Kindle Keyboard

- Press the **Menu** button
- Go to **Settings** and select
- Look for **Device Info** to get your Kindle's Wi-Fi MAC address

Kindle Touch / Kindle Paperwhite

- Press the **Menu** button
- Go to **Settings** and select
- From **Settings** select Menu again
- Look for **Device Info** to get your Kindle's Wi-Fi MAC address

Kindle Fire

- Tap on the **Settings** icon
- Tap on **More**
- Tap on the **Device** option in the **Settings** page
- Here you will see your **Wi-Fi MAC Address**

Android Tablet

- On the Home screen, tap the **Menu** button and go to **Settings**
- Scroll down and tap **About Device** then tap **Status** and then scroll down to view Wi-Fi MAC address

Windows 7 Device

- Click the **Start** menu button on the Windows taskbar.
- Click **All Programs**
- Click **Accessories**
- Click **Command Prompt**
- In this command window, type **ipconfig /all** Details are shown for each of the computer's network adapters.
- Look for **Wireless Adapter Wi-Fi section**. The **Physical Address** field states that MAC address for that adapter.

Windows 8 Device

- From the Metro UI, right-click on the bottom left corner.
- Click **Command Prompt**
- In this command window, type **ipconfig /all** Details are shown for each of the computer's network adapters.
- Look in the **Wireless Adapter Wi-Fi section**. The **Physical Address** field states that MAC address for that adapter

Apple Mac OS X

- From the **Apple** in the upper left hand corner choose System Preferences
- Click on the **Network** icon
- Select **Wi-Fi** for **Wireless**
- Click on the **Advanced** button
- Your MAC address will be at the bottom of this window as your **Wi-Fi Address**

Google Chromebook

- From a browser tab, enter **chrome://system** in the URL field and press **Enter**.
- From the **ifconfig**, click **Expand**.
- The MAC address of the Chromebook will be displaying in the **wlan0** section.

If you have a device type that is not listed here, or if you are still unsure of how to find your device MAC Address, please contact Mrs. Fairley at martha.fairley@eagleslanding.org or 678-818-1056.